

Right Rate

Adjusting soil pH is no easy task. It is a slow- and long-term process that will usually require several tons of lime over multiple years. It's important to know exactly how much to apply to be both productive and economical. There are two main factors to look at when determining how much lime to apply:

Soil test results

Testing your soil is THE most important thing you can do to determine the correct amount of lime you need to apply.

The crop or plant to be grown

Different plants desire different pH levels. Do not exceed applications greater than 2.5 tons per acre. If the soil requires more than that, split the recommendation into two separate applications and apply them at least three to four months apart.

Right Time

In general, lime can be applied year around. For the Pacific Northwest, there may be a slight advantage to applying it in the fall so the lime can be drawn down further into the soil profile during our rainy winter months. Lime usually takes three to four months to fully react with the soil. By applying it in the fall, this reaction can take place in advance of the spring planting/growing season.

Right Place

It's best to till in lime to reduce losses from rain run-off and wind, and increase the amount of surface area exposed to your soil, allowing a faster reaction. Top-dressing is also a viable application method. A broadcast spreader is commonly used to apply lime. Pelleted lime works best in a broadcast spreader. If you don't have one, you can contact the Conservation District to rent a pull-type spreader for liming your fields and pastures.



Right Source

When choosing the right source of lime, you want to look for three main things: purity or neutralizing value, particle size, and cost.

Purity or Neutralizing Value

Neutralizing value is expressed as a percentage of calcium carbonate equivalent (CCE), where pure calcium carbonate (CaCO₃) is set at 100 percent. The higher the CCE, the greater the liming effect.

Some aglime, such as dolomitic limestone, can have a rating higher than 100 percent. Aglime usually contains impurities such as clays, sand, and organic matter, which reduce CCE.

Particle Size

Often called "fineness of grind", this factor determines how rapidly aglime will react and neutralize soil acidity. The finer the grind - the quicker it reacts and neutralizes.

- The down-side to a finer grind is that wind can be an issue during application. Also, in situations where appearance is a factor, use a pelletized form to prevent everything from being covered in lime dust.
- Some plants and crops do not like quick changes in pH, so a larger particle size may be desired to provide a more gradual/slower change.

Cost

Economics is always important. Always look at the calcium carbonate equivalent percentage (CCE) to determine the actual amount of liming effect you are purchasing.

Caution

Always use an Ag lime and not a chemical lime as it can burn.

Get Your Soil Tested - FREE!

If you'd like your soil tested, please contact the Snohomish Conservation District to enroll in our 'Free Soil Testing Program'. We can also help you put together a soil nutrient management plan specifically tailored for your needs and operation.

Questions?

If you have questions regarding the application of lime or soil testing, please contact one of our farm planners at 425-335-5634 or farmplanners@snohomishcd.org.